

CONTENTS

•	SYSTEM REQUIREMENTS	2
•	INSTALLATION STEPS FOR WINDOWS XP	3
•	INSTALLATION STEPS FOR WINDOWS VISTA / WINDOWS 7	1
	GENERAL USAGE	1


SYSTEM REQUIREMENTS

The following system requirements need to be ensured:

- An Intel compatible PC with an Intel Pentium III CPU running at 1GHz clock speed or higher
- Alternatively an i686 compatible CPU from other vendors with equal performance to the above specification
- Hard disk with at least 1GB of free space
- Windows XP with service pack 3 or Windows Vista / Windows 7 32
 Bit edition
- · Ethernet card
- Thuraya IP terminal

The following steps need to be done for a successfull installation under the operating system Windows XP:

- Locate the file called "tcpa_2.6.11_thurayalP.exe" and double click on it.
 This will start the installation process (Administrator mode)
- The welcome message will appear on the screen. Please click "Next" to proceed with the installation



 You may select the destination folder to install the client or use the default path. Click "Next" once confirmed



• The Program Manager Group will be highlighted, click "Next" to continue




• Click "Next" to confirm and proceed with the installation



In order to use the "transparent mode", a special driver has to be installed
on the system. A warning will appear with a notification that the driver is
not verified by Windows. You may continue by clicking "Continue anyway".
 This driver was tested and verified by Thuraya



 When the message below appears, click "Finish" to complete the installation




• Finally, you can find the installed application in the start menu



The following steps need to be done for a successful installation under the operating systems Windows VISTA / Windows 7:

 Locate the file called "tcpa_2.6.11_thurayalP.exe". Right click on it and choose "Run as administrator" from the context menu. This will start the installation process.

INSTALLATION STEPS FOR WINDOWS VISTA / WINDOWS 7



 The welcome message will appear on the screen. Please click "Next" to proceed with the installation



 You may select the destination folder to install the client or use the default path. Click "Next" once confirmed



The Program Manager Group will be highlighted. Click
 "Next" to continue



Click "Next" to confirm and proceed with the installation




A warning will appear with a notification that the driver is not verified by Windows. You may continue by clicking "Install this driver software anyway". This driver was tested and verified by Thuraya



 When the message below appears click "Finish" to complete the installation



Finally, you can find the installed application in the start menu



 After the initial attempt to start the client, you might be prompted by Windows firewall asking you if you would like to unblock the client. Please click on "Unblock"



GENERAL USAGE

After the completion of the installation process, the user has the choice of either using the client in proxy mode or in a transparent mode which does not require any further user input.

Proxy mode:

- Go to the proxy settings in your browser and configure localhost:8080 as the proxy
- · Locate the client in the start menu and start it by clicking on it

Transparent mode:

Locate the client in the start menu, do a "right click" on it and select "run as administrator"

On a successful start, a blue tray icon will be displayed.



To stop the application right click on the tray icon and choose "Exit".

Thuraya Customer Care Center From Thuraya network: 100 From other networks: +88216 100 100 Fax: +971 6 8828444 Email: customer.care@thuraya.com